

Package ‘adbcpostgresql’

September 6, 2024

Title 'Arrow' Database Connectivity ('ADBC') 'PostgreSQL' Driver

Version 0.14.0

Description Provides a developer-facing interface to the 'Arrow' Database Connectivity ('ADBC') 'PostgreSQL' driver for the purposes of building high-level database interfaces for users. 'ADBC' <<https://arrow.apache.org/adbc/>> is an API standard for database access libraries that uses 'Arrow' for result sets and query parameters.

License Apache License (>= 2)

Encoding UTF-8

RoxygenNote 7.2.3

SystemRequirements libpq

Suggests nanoarrow, testthat (>= 3.0.0)

Config/testthat/edition 3

Config/build/bootstrap TRUE

URL <https://github.com/apache/arrow-adbc>,
<https://arrow.apache.org/adbc/current/r/adbcpostgresql/>

BugReports <https://github.com/apache/arrow-adbc/issues>

Imports adbcdrivermanager

NeedsCompilation yes

Author Dewey Dunnington [aut, cre] (<<https://orcid.org/0000-0002-9415-4582>>),
Apache Arrow [aut, cph],
Apache Software Foundation [cph]

Maintainer Dewey Dunnington <dewey@dunnington.ca>

Repository CRAN

Date/Publication 2024-09-06 07:50:06 UTC

Contents

adbcpostgresql	2
Index	4

adbcpostgresql *ADBC PostgreSQL Driver*

Description

ADBC PostgreSQL Driver

Usage

```
adbcpostgresql()

## S3 method for class 'adbcpostgresql_driver_postgresql'
adbc_database_init(driver, ..., uri)

## S3 method for class 'adbcpostgresql_database'
adbc_connection_init(database, ..., adbc.connection.autocommit = NULL)

## S3 method for class 'adbcpostgresql_connection'
adbc_statement_init(
  connection,
  ...,
  adbc.ingest.target_table = NULL,
  adbc.ingest.mode = NULL
)
```

Arguments

driver	An adbc_driver() .
...	Driver-specific options. For the default method, these are named values that are converted to strings.
uri	A URI to a database path (e.g., postgresql://localhost:1234/postgres?user=user&password=pass).
database	An adbc_database .
adbc.connection.autocommit	Use FALSE to disable the default autocommit behaviour.
connection	An adbc_connection
adbc.ingest.target_table	The name of the target table for a bulk insert.
adbc.ingest.mode	Whether to create (the default) or append.

Value

An [adbcdrivermanager::adbc_driver\(\)](#)

Examples

`adbcpostgresql()`

Index

`adb_connection`, [2](#)
`adb_connection_init.adbpostgresql_database`
 (`adbpostgresql`), [2](#)
`adb_database`, [2](#)
`adb_database_init.adbpostgresql_driver_postgresql`
 (`adbpostgresql`), [2](#)
`adb_driver()`, [2](#)
`adb_statement_init.adbpostgresql_connection`
 (`adbpostgresql`), [2](#)
`adbdrivermanager::adb_driver()`, [2](#)
`adbpostgresql`, [2](#)